

PolSARpro v6.0 (Biomass Edition)

POLARIMETRIC DATA FORMAT

Description

This help file describes the different and specific PolSARpro v6.x (Biomass Edition) compatible raw binary data formats.

PolSARpro v6.x (Biomass Edition) can process fully polarimetric or partially polarimetric data sets under many different formats.


A polarimetric data set is composed of **Binary files** characterized by a **Configuration Text File** and located in a given **Data Directory.**



Configuration Text File

A Configuration text file is automatically created by the different data processing applications proposed in PolSARpro and by any conversion from sensor specific format data.

PolSARpro offers the possibility to directly process polarimetric data binary files. In this case, users have to provide a configuration text file named config.txt and formatted as follows:






Binary Data Files (1/2)

In order to be correctly interpreted by PolSARpro, binary data files have to be built according to a compatible format.

 A Nrow x Ncol image is read by PolSARpro on a row by row basis, i.e. Ncol pixels are read in a single thread and are then assigned to one of the rows of a Nrow x Ncol matrix as shown in the following illustration.





Binary Data Files (2/2)

- Binary data associated to real (not complex) variables are coded under the form of 4-bytes (i.e. 32 bits) float numbers. A Nrow x Ncol image of a real variable (e.g T₁₁) contains Nrow*Ncol*4 bytes, i.e. Nrow*Ncol*32 bits.
- Binary data associated to complex variables are coded under the form of interlaced 4-bytes float numbers representing real and imaginary parts.


A Nrow x Ncol image of a complex variable (e.g s_{11}) contains Nrow*Ncol*2*4 bytes, i.e. Nrow*Ncol*2*32 bits.

$$\left\{T_{i,1} \quad \cdots \quad T_{i,j} \quad \cdots \quad T_{i,Ncol}\right\}$$

$$\left\{\Re\left(s_{i,I}\right),\ \Im\left(s_{i,I}\right),\ \cdots\ \Re\left(s_{i,j}\right),\ \Im\left(s_{i,j}\right),\ \cdots\ \Re\left(s_{i,Ncol}\right)\right\}$$


Schematic description of one row with Ncol real (T_{11}) or complex (S_{11}) elements

Dual data sets Pol-InSAR data format




- S: Single polarimetric data set (PolSAR mode)
- D : Dual polarimetric data sets (Single Baseline Pol-InSAR mode)
- M: Multi polarimetric data sets (Time series Pol-TimeSAR mode)
 Tomography Pol-TomoSAR mode)






- **S**: Single polarimetric data set (PolSAR mode)
 - [S2]: (2x2) complex Sinclair matrix
 - (Sxx, Sxy): (2x1) dual-pol complex vector
 - [C2]: (2x2) dual-pol covariance [C2] matrix
 - [C3]: (3x3) full-pol covariance [C3] matrix
 - [C4]: (4x4) full-pol covariance [C4] matrix
 - [T2]: (2x2) dual-pol coherency [T2] matrix
 - [T3]: (3x3) full-pol coherency [T3] matrix
 - [T4]: (4x4) full-pol coherency [T4] matrix





- **D**: Dual polarimetric data sets (Single Baseline Pol-InSAR mode)
 - [S2]: (2x2) complex Sinclair matrix (Master / Slave)
 - (Sxx, Sxy): (2x1) dual-pol complex vector (Master / Slave)
 - [T4]: (4x4) dual-pol coherency [T4] matrix (Master + Slave)
 - [T6]: (6x6) full-pol coherency [T6] matrix (master + Slave)

3x3) and (4x4) coherency [T3] and [T4] matrices



- M: Multi polarimetric data sets (Time series Pol-TimeSAR mode Tomography – Pol-TomoSAR mode)
 - [S2]: (2x2) complex Sinclair matrix
 - (Sxx, Sxy): (2x1) dual-pol complex vector
 - [C2]: (2x2) dual-pol covariance [C2] matrix
 - [T3]: (3x3) full-pol coherency [T3] matrix

(2x2) complex Sinclair [S₂] matrix (1/2)

This matrix is a coherent polarimetric representation relating incident and scattered Jones vectors.

In a general case, it is composed of four complex elements and becomes symmetric in monostatic configurations.

$$\begin{bmatrix} S_2 \end{bmatrix} = \begin{bmatrix} S_{11} & S_{12} \\ S_{21} & S_{22} \end{bmatrix}$$

The (2x2) complex Sinclair $[S_2]$ raw binary data files have to be located in the User Main Data Directory (MDD) and described by a configuration text file.

(2x2) complex Sinclair [S₂] matrix (2/2)

Contents of the User Main Data Directory (MDD):

```
    ~ MDD / ..
    ~ MDD / ..
    ~ MDD / config.txt
    ~ MDD / s11.bin
    ~ MDD / s12.bin
    ~ MDD / s21.bin
    ~ MDD / s21.bin
```

Important Note: PolSARpro requires distinct s12.bin and s21.bin data files, even in monostatic configurations.

Some polarimetric data sets only present a single cross-polarization channel, e.g. s12.bin. Users have then to create a second cross-polarization channel, e.g. copy s12.bin to s21.bin.

- PolarType = full
- If [S₂] matrix is symmetric (s12 = s21): PolarCase = monostatic
- If [S₂] matrix is non symmetric (s12 != s21) : PolarCase = bistatic



(3x3) coherency $[T_3]$ matrix (1/2)

- This matrix is an incoherent polarimetric representation relating to second order statistics of scattering matrix elements.
- This matrix is hermitian semi-definite positive.
- This matrix is constructed from a three-element unitary target vector, obtained from the projection of a Sinclair matrix onto a reduced and modified Pauli spin matrix set. An outter product leads to the definition of the corresponding (3x3) Coherency matrix [T₃] relating to second order statistics.

$$\vec{k}_{3P} = \frac{1}{\sqrt{2}} \begin{bmatrix} s_{11} + s_{22} & s_{11} - s_{22} & s_{12} + s_{21} \end{bmatrix}^T$$

$$\Rightarrow [T_3] = \langle \vec{k}_{3P} \cdot \vec{k}_{3P}^{T*} \rangle = \begin{bmatrix} T_{11} & T_{12} & T_{13} \\ T_{12}^* & T_{22} & T_{23} \\ T_{13}^* & T_{23}^* & T_{33} \end{bmatrix}$$



The (3x3) coherency $[T_3]$ raw binary data files have to be located in the User Main Data Directory (MDD) and described by a configuration text file.

Contents of the User Main Data Directory (MDD):

```
      "~ MDD / ..
      "~ MDD / T13_real.bin

      "~ MDD / ..
      "~ MDD / T13_imag.bin

      "~ MDD / config.txt
      "~ MDD / T22.bin

      "~ MDD / T11.bin
      "~ MDD / T23_real.bin

      "~ MDD / T12_real.bin
      "~ MDD / T23_imag.bin

      "~ MDD / T33.bin
      "~ MDD / T33.bin
```

Note: Txy_real.bin and Txy_imag.bin denote respectively real and imaginary part of a coherency matrix complex element.

- PolarType = full
- PolarCase = monostatic



(4x4) coherency $[T_4]$ matrix (1/2)

- This matrix is an incoherent polarimetric representation relating to second order statistics of scattering matrix elements.
- This matrix is hermitian semi-definite positive.
- This matrix is constructed from a four-element unitary target vector, obtained from the projection of a Sinclair matrix onto a reduced and modified Pauli spin matrix set. An outter product leads to the definition of the corresponding (4x4) Coherency matrix [T₄] relating to second order statistics.

$$\vec{k}_{4P} = \frac{1}{\sqrt{2}} \begin{bmatrix} s_{11} + s_{22} & s_{11} - s_{22} & s_{12} + s_{21} & j(s_{12} - s_{21}) \end{bmatrix}^{T}$$

$$\Rightarrow \begin{bmatrix} T_{4} \end{bmatrix} = \langle \vec{k}_{4P} \cdot \vec{k}_{4P}^{T*} \rangle = \begin{bmatrix} T_{11} & T_{12} & T_{13} & T_{14} \\ T_{12}^{*} & T_{22} & T_{23} & T_{24} \\ T_{13}^{*} & T_{23}^{*} & T_{33} & T_{34} \\ T_{14}^{*} & T_{24}^{*} & T_{34}^{*} & T_{44} \end{bmatrix}$$

(4x4) coherency $[T_4]$ matrix (2/2)

The (4x4) coherency [T₄] raw binary data files have to be located in the User Main Data Directory (MDD) and described by a configuration text file.

Contents of the User Main Data Directory (MDD):

```
•~ MDD / T22.bin
•~ MDD / .
•~ MDD / ..
■~ MDD / config.txt
•~ MDD / T11.bin
•~ MDD / T12 real.bin
•~ MDD / T12 imag.bin
•~ MDD / T13 real.bin
•~ MDD / T13_imag.bin
•~ MDD / T14 real.bin
•~ MDD / T14 imag.bin
```

•~ MDD / T23 real.bin •~ MDD / T23 imag.bin •~ MDD / T24 real.bin •~ MDD / T24 imag.bin •~ MDD / T33.bin •~ MDD / T34 real.bin •~ MDD / T34 imag.bin •~ MDD / T44.bin

Note: Txy_real.bin and Txy_imag.bin denote respectively real and imaginary part of a coherency matrix complex element.

- PolarType = full
- PolarCase = bistatic



(3x3) covariance $[C_3]$ matrix (1/2)

- This matrix is an incoherent polarimetric representation relating to second order statistics of scattering matrix elements.
- This matrix is hermitian semi-definite positive.
- This matrix is constructed from a three-element unitary target vector, obtained from the projection of a Sinclair matrix onto a reduced and modified Lexicographic matrix set. An outter product leads to the definition of the corresponding (3x3) Covariance matrix [C₃] relating to second order statistics.

$$\vec{k}_{3L} = \begin{bmatrix} s_{11} & \sqrt{2}s_{12} & s_{22} \end{bmatrix}^{T}$$

$$\Rightarrow \begin{bmatrix} C_{3} \end{bmatrix} = \langle \vec{k}_{3L} \cdot \vec{k}_{3L}^{T*} \rangle = \begin{bmatrix} C_{11} & C_{12} & C_{13} \\ C_{12}^{*} & C_{22} & C_{23} \\ C_{13}^{*} & C_{23}^{*} & C_{33} \end{bmatrix}$$

(3x3) covariance $[C_3]$ matrix (2/2)

The (3x3) covariance $[C_3]$ raw binary data files have to be located in the User Main Data Directory (MDD) and described by a configuration text file.

Contents of the User Main Data Directory (MDD):

```
    MDD / .
    MDD / C13_real.bin
    MDD / C13_imag.bin
    MDD / C22.bin
    MDD / C11.bin
    MDD / C23_real.bin
    MDD / C23_imag.bin
    MDD / C33.bin
```

Note: Cxy_real.bin and Cxy_imag.bin denote respectively real and imaginary part of a covariance matrix complex element.

- PolarType = full
- PolarCase = monostatic



(4x4) covariance $[C_4]$ matrix (1/2)

- This matrix is an incoherent polarimetric representation relating to second order statistics of scattering matrix elements.
- This matrix is hermitian semi-definite positive.
- This matrix is constructed from a four-element unitary target vector, obtained from the projection of a Sinclair matrix onto a reduced and modified Lexicographic matrix set. An outter product leads to the definition of the corresponding (4x4) Covariance matrix [C₄] relating to second order statistics.

$$\vec{k}_{4L} = \begin{bmatrix} s_{11} & s_{12} & s_{21} & s_{22} \end{bmatrix}^{T}$$

$$\Rightarrow \begin{bmatrix} C_{4} \end{bmatrix} = \langle \vec{k}_{4L} \cdot \vec{k}_{4L}^{T*} \rangle = \begin{bmatrix} C_{11} & C_{12} & C_{13} & C_{14} \\ C_{12}^{*} & C_{22} & C_{23} & C_{24} \\ C_{13}^{*} & C_{23}^{*} & C_{33} & C_{34} \\ C_{14}^{*} & C_{24}^{*} & C_{34}^{*} & C_{44} \end{bmatrix}$$



(4x4) covariance $[C_4]$ matrix (2/2)

The (4x4) covariance $[C_4]$ raw binary data files have to be located in the User Main Data Directory (MDD) and described by a configuration text file.

Contents of the User Main Data Directory (MDD):

```
•~ MDD / C22.bin
•~ MDD / .
•~ MDD / ..
                                   •~ MDD / C23 real.bin
■~ MDD / config.txt
                                   •~ MDD / C23 imag.bin
•~ MDD / C11.bin
                                   •~ MDD / C24 real.bin
                                   •~ MDD / C24_imag.bin
•~ MDD / C12 real.bin
•~ MDD / C12 imag.bin
                                   •~ MDD / C33.bin
                                   •~ MDD / C34 real.bin
•~ MDD / C13 real.bin
•~ MDD / C13_imag.bin
                                   •~ MDD / C34 imag.bin
                                   •~ MDD / C44.bin
•~ MDD / C14 real.bin
•~ MDD / C14 imag.bin
```

Note: Cxy_real.bin and Cxy_imag.bin denote respectively real and imaginary part of a coherency matrix complex element.

- PolarType = full
- PolarCase = bistatic

(2x1) dual-polarimetric (Sxx, Sxy) vector (1/2)

This vector is a coherent polarimetric representation of a scattered Jones vector.

It is composed of two complex elements.

There exist three different combinations which are the following:

```
    Partial polarimetry mode 1 (pp1): (Sxx, Sxy) ≡ {s11, s21}
    Partial polarimetry mode 2 (pp2): (Sxx, Sxy) ≡ {s12, s22}
```

•Partial polarimetry mode 3 (pp3): (Sxx, Sxy) ≡ {s11, s22}

The (2x1) complex (Sxx, Sxy) raw binary data files have to be located in the User Main Data Directory (MDD) and described by a configuration text file.

(2x1) dual-polarimetric (Sxx, Sxy) vector (2/2)

Contents of the User Main Data Directory (MDD):

```
pp3 mode:
pp1 mode:
                        pp2 mode:
                                                  •~ MDD / .
  •~ MDD / .
                          •~ MDD / .
                                                  •~ MDD / ..
  •~ MDD / ..
                          •~ MDD / ..
  •~ MDD / config.txt
                          ■~ MDD / config.txt
                                                  ■~ MDD / config.txt
  •~ MDD / s11.bin
                                                  •~ MDD / s11.bin
                          •~ MDD / s12.bin
  •~ MDD / s21.bin
                          •~ MDD / s22.bin
                                                  •~ MDD / s22.bin
```

- PolarCase = monostatic
- PolarType = pp1 or pp2 or pp3



(2x2) dual-polarimetric covariance [C₂] matrix (1/2)

- This matrix is an incoherent polarimetric representation relating to second order statistics of a Jones vector.
- This matrix is hermitian semi-definite positive.
- This matrix is constructed from a two-element Jones vector and an outter product leads to the definition of the corresponding (2x2) Covariance matrix [C₂] relating to second order statistics.

$$\vec{k}_{2L} = \begin{bmatrix} s_{xx} & s_{xy} \end{bmatrix}^{T}$$

$$\Rightarrow \begin{bmatrix} C_{2} \end{bmatrix} = \langle \vec{k}_{2L} \cdot \vec{k}_{2L}^{T*} \rangle = \begin{bmatrix} C_{11} & C_{12} \\ C_{12}^{*} & C_{22} \end{bmatrix}$$

(2x2) dual-polarimetric covariance [C₂] matrix (2/2)

The (2x2) covariance $[C_2]$ raw binary data files have to be located in the User Main Data Directory (MDD) and described by a configuration text file.

Contents of the User Main Data Directory (MDD):

```
"~ MDD / .
"~ MDD / ..
"~ MDD / config.txt
"~ MDD / C11.bin
"~ MDD / C12_real.bin
"~ MDD / C12_imag.bin
"~ MDD / C22.bin
```

Note: Cxy_real.bin and Cxy_imag.bin denote respectively real and imaginary part of a covariance matrix complex element.

- PolarCase = monostatic
- PolarType = pp1 or pp2 or pp3

Dual data sets Pol-InSAR data format



Dual-polarimetric Pol-InSAR data format

$$\left\{S_{xx}^{S} - S_{xy}^{S}\right\}$$

$$\vec{k}_{2P}^{M} = \frac{1}{\sqrt{2}} \left[s_{xx}^{M} - s_{xy}^{M} \quad s_{xx}^{M} + s_{xy}^{M} \right]^{T}$$

$$\vec{k}_{2P}^{M} = \frac{1}{\sqrt{2}} \left[s_{xx}^{M} - s_{xy}^{M} \quad s_{xx}^{M} + s_{xy}^{M} \right]^{T} \qquad \vec{k}_{2P}^{S} = \frac{1}{\sqrt{2}} \left[s_{xx}^{S} - s_{xy}^{S} \quad s_{xx}^{S} + s_{xy}^{S} \right]^{T}$$

$$\vec{k}_{4P}^{M+S} = \begin{bmatrix} \vec{k}_{2P}^{M} & \vec{k}_{2P}^{S} \end{bmatrix}^{T}$$

Master MDD_Slave MDD

$$\Rightarrow \begin{bmatrix} T_{4}^{M+S} \end{bmatrix} = \left\langle \vec{k}_{4P}^{M+S} \cdot (\vec{k}_{4P}^{M+S})^{T*} \right\rangle = \begin{bmatrix} T_{11}^{M} & T_{12}^{M} & \Omega_{11} & \Omega_{12} \\ T_{21}^{M} & T_{22}^{M} & \Omega_{21} & \Omega_{22} \\ \Omega_{11}^{*} & \Omega_{12}^{*} & T_{11}^{S} & T_{12}^{S} \\ \Omega_{21}^{*} & \Omega_{22}^{*} & T_{21}^{S} & T_{22}^{S} \end{bmatrix}$$

Full-polarimetric Pol-InSAR data format (1/2)

$$\vec{k}_{3P}^{M} = \frac{1}{\sqrt{2}} \left[s_{11}^{M} + s_{22}^{M} \quad s_{11}^{M} - s_{22}^{M} \quad s_{12}^{M} + s_{21}^{M} \right]^{T}$$

$$\vec{k}_{3P}^{S} = \frac{1}{\sqrt{2}} \left[s_{11}^{S} + s_{22}^{S} \quad s_{11}^{S} - s_{22}^{S} \quad s_{12}^{S} + s_{21}^{S} \right]^{T}$$

$$\vec{k}_{6P}^{M+S} = \begin{bmatrix} \vec{k}_{3P}^{M} & \vec{k}_{3P}^{S} \end{bmatrix}^{T}$$



Full-polarimetric Pol-InSAR data format (2/2)

$$\vec{k}_{6P}^{M+S} = \begin{bmatrix} \vec{k}_{3P}^{M} & \vec{k}_{3P}^{S} \end{bmatrix}^{T}$$

Master MDD_Slave MDD

$$\Rightarrow \left[T_{6}^{M+S}\right] = \left\langle \vec{k}_{6P}^{M+S} \cdot \left(\vec{k}_{6P}^{M+S}\right)^{T*} \right\rangle = \begin{bmatrix} T_{11}^{M} & T_{12}^{M} & T_{13}^{M} & \Omega_{11} & \Omega_{12} & \Omega_{13} \\ T_{21}^{M} & T_{22}^{M} & T_{23}^{M} & \Omega_{21} & \Omega_{22} & \Omega_{23} \\ T_{31}^{M} & T_{32}^{M} & T_{33}^{M} & \Omega_{31} & \Omega_{32} & \Omega_{33} \\ \hline \Omega_{11}^{*} & \Omega_{12}^{*} & \Omega_{13}^{*} & T_{11}^{S} & T_{11}^{S} & T_{11}^{S} \\ \Omega_{21}^{*} & \Omega_{22}^{*} & \Omega_{23}^{*} & \Omega_{33}^{*} & T_{11}^{S} & T_{11}^{S} & T_{11}^{S} \end{bmatrix}$$

